

Invert Long Documents

This chapter covers the following topics:

- Description
- Procedure
- Batch Example

Description

Program

B10000

Function

Invert TRS documents which are filed in folder TRS-XXL.

TRS documents are automatically moved to the TRS-XXL folder whenever a user manages (issues commands such as MODIFY, FILE, TRANSLATE) a TRS document which is longer than the length allowed to be inverted online.

The maximum length of a document which can be inverted online is specified in the system defaults. See *Con-nect Text Retrieval Administration* in *Con-nect Administration* for further information.

Online Input Screen

12:52 PM	* * * C O N - N E C T 3 * * *	14.Feb.94
Cabinet LS	Invert Long Documents	B10000

Invert Documents filed in folder TRS-XXL

From Cabinet _____ to Cabinet _____

('*' for all cabinets)

(This function is only supported if TRS is available)

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
 Menu Quit

Complete the information above and press ENTER to continue

Utility Parameters

Parameter	Format	Description
From Cabinet	A8	
To Cabinet	A8	Optional

Procedure

Whenever a user manages a TRS document (i.e. issues a command such as MODIFY, FILE, TRANSLATE), that document is inverted online. If the document is longer than the length allowed to be inverted online, the document is automatically filed in the folder TRS-XXL. Although the document is not inverted until the utility is run, the user can continue to access and modify the document.

When this utility is run, it inverts the document(s) from the specified cabinet(s) stored in the TRS-XXL folder. The inverted document(s) is then moved back to the source TRS folder or the new folder which was specified while filing the document(s).

If a document from cabinet SYSCNT is filed in the folder TRS-XXL, it is inverted when cabinet SYSCNT is the only cabinet specified in the parameters start cabinet and end cabinet. If a range of cabinets is specified, documents from cabinet SYSCNT are not inverted.

If an error occurs during the inversion process, the user is notified and the document remains in folder TRS-XXL.

Note:

TRS must be active when this utility is run.

Batch Example

Invert all TRS documents in the folder TRS-XXL from cabinet LS. This would be coded as follows:

```
LOGON SYSCNT2B
MENU
B10000 LS,LS
FIN
```